

Net Contents: 500ml



MAPP 19246

HOW TO USE: Shake the TRICO GARDEN container prior to opening. Dilute TRICO GARDEN at a ratio of 1 part product in 3 parts water (1:3) to 1 part product in 5 parts water (1:5) and apply using a sprayer fitted with a medium nozzle. 150 - 200mls TRICO GARDEN are applied in a final volume of 0.3 - 1.0l/100m².

APPLICATION: Rate: TRICO GARDEN should be applied as a dilute spray to trees, shrubs and ornamental plants. For specimen trees a rate of 12 - 20mls/tree should be used. **Timing:** At the first signs of damage. **In the Autumn:** a single application may be sufficient to repel deer but if the risk of damage persists a second application can be made 28 days after the first application. **In the Spring:** a single application may be sufficient to repel deer but if the risk of damage persists a maximum of three repeat applications can be made at 28 days intervals.

NOTE: A maximum of four applications are permitted per annum. During hot weather carry out the application in the morning or evening as in high temperatures and intense sunlight there is a risk of damage to soft tissue such as leaves and young shoots. To be effective the application must dry on the target.

PLANT SAFETY: TRICO GARDEN has been found to be safe to use on all species of hardwoods and conifers during the autumn/winter period of use. In addition no phytotoxic effects following a spring/summer application have been recorded on the following plant species:

Geranium sp.	Roses	Daisies	Viola sp
Forsythia sp.	Laburnum	Weigela	Begonias
			Salvia sp.

It is strongly recommended that a single plant is treated first to ascertain whether phytotoxic effects are evident before treating large areas. In addition the recommendations in the HOW TO USE section should be followed.

A deer repellent containing 64.6 g/L sheep fat as an oil in water emulsion for use in the garden to reduce damage caused by browsing deer.

WHERE TO USE: TRICO GARDEN is a repellent by smell. The dilute spray is applied to vulnerable parts of ornamental plants, shrubs and trees to reduce damage caused by deer browsing. The smell of sheep fat keeps deer away from treated plant material and hence reduces damage by browsing.

FOR USE ONLY AS AN AMATEUR ANIMAL REPELLENT

Crops/situations	Maximum individual dose mls/100m ²	Maximum number of treatments	Application interval
All trees, shrubs and ornamental garden plants	200	4	28 days

USE PESTICIDES SAFELY, READ THE LABEL

DO NOT apply TRICO GARDEN with any other plant protection product. **DO NOT** apply other plant protection products one week before and one week after application of TRICO GARDEN. **DO NOT** apply if rainfall is expected before the spray dries on the target. If rain occurs before the deposit dries reapplication will be necessary. Care must be taken to avoid drift onto non-target plants and food crops.

Producer: Kwizda Agro GmbH, Universitätsring 6, A-1010 Vienna. Tel: +43 5 99 77 10

Kwizda

Agro

Distributor: Laronkarn Ltd., Chartwell House, 38 Church Street, Malvern, WORCS, WR14 2AZ. Tel: 01684 899 306

TRICO GARDEN

Contains 64.6 g/L sheep fat and a mixture of: 5-chloro-2-methyl-4-isothiazolin-3-one and 2-methyl-2H-isothiazol-3-one (3:1). May produce an allergic reaction.

IF MEDICAL ADVICE IS NEEDED HAVE PRODUCT CONTAINER OR LABEL TO HAND. KEEP OUT OF REACH OF CHILDREN. DO NOT GET IN EYES, ON SKIN OR ON CLOTHING. DO NOT EAT, DRINK OR SMOKE WHEN USING THE PRODUCT. WEAR PROTECTIVE GLOVES. DISPOSE OF CONTENTS/CONTAINER TO A RECYCLING CENTRE AS HAZARDOUS WASTE EXCEPT CONTAINERS WHICH CAN BE DISPOSED OF IN THE DUSTBIN. CONTACT YOUR LOCAL COUNCIL FOR DETAILS.

To avoid risk to human health and the environment comply with instructions for use. Do not contaminate water with the product or its container.

SAFETY INSTRUCTIONS

Protection during use. WASH HANDS AND EXPOSED SKIN after use/handling.

Environmental protection. DO NOT CONTAMINATE WATER with the product or its container. DO NOT empty into drains. Direct spray away from ponds and other surface water bodies

Storage and disposal. KEEP AWAY FROM FOOD AND DRINK. KEEP IN ORIGINAL CONTAINER tightly closed, in a safe place. KEEP PRODUCT AWAY FROM CHILDREN AND PETS. Dispose of empty container in the dustbin. PROTECT FROM FROST

C074117-01